


Adapter Validation Tool

User Manual



DG Technologies
33604 West Eight Mile Road
Farmington Hills, MI 48335
Phone (248) 888-2000
Fax (248) 888-9977

Document Revision: 1.04
Document Date: January 3, 2023
Copyright: 2022 DG Technologies

Permission is granted to copy any or all portions of this manual, provided that such copies are for use with the DPA product and that “© 2012-2023 Dearborn Group, Inc.”, (herein referred to as “Dearborn Group”, “DG Technologies”, or “DG”), remains on all copies.

IMPORTANT

To ensure your success with this product, it is essential that you read this document carefully before using the hardware.

Damage caused by misuse of the hardware is not covered under product warranty. When using this manual, please remember the following:

- This manual may be changed, in whole or in part, without notice.
- DG assumes no responsibility for any damage resulting from the use of this hardware or software.
- Specifications presented herein are provided for illustration purposes only and may not accurately represent the latest revisions of hardware, software or cabling.
- No license is granted, by implication or otherwise, for any patents or other rights of DG or of any third party.

DG® logo is a registered trademark of DG Technologies, Inc. Other products that may be referenced in this manual are trademarks of their respective manufacturers.

DG understands that there are numerous safety hazards that cannot be foreseen, so we recommend that the user read and follow all safety messages in this manual, on all your shop equipment, from your vehicle manuals, as well as internal shop documents and operating procedures.

1 Table of Contents

2 Safety First.....	4
3 Troubleshooting Diagnostic Tool with Adapter Validation Tool (AVT)	4
3.1 Adapter Validation Tool Startup.....	4
3.2 Select the Correct AVT Launcher Button	5
3.2.1 MD/HD Button	5
3.2.2 OBDII Button	5
4 Adapter Validation Tool for Heavy and Medium-Duty Vehicles	5
4.1 AVT HD Automated Testing	6
4.1.1 Select the Diagnostic Tool.....	6
4.1.2 Run the Automated Test.....	6
4.1.3 RP1210 Status Window (PC – VDA)	7
4.1.4 Protocol Status.....	9
4.2 Advanced Testing Dialog (Vendor/Device/Protocol)	10
4.2.1 Baud Rate Drop Down List Box	11
4.2.2 Channel Drop Down List Box.....	11
4.2.3 Vendor Supports CAN Auto Baud Checkbox.....	11
4.2.4 Protocols Supporting Baud=XXX	11
4.2.5 Advanced Testing Commands – No Error Checking	11
4.2.6 RP1210 Data Message Window	11
4.3 Not Seeing Diagnostic Tool device in HD OEM Application VDA Selection List	12
4.3.1 Fix INI Application	12
5 AVT (OBDII) – Adapter Validation Tool for Light and Medium-Duty Vehicles	13
5.1 AVT OBDII Automated Test	14
5.1.1 Configure Device	14
5.1.2 Run Test	14
5.1.3 AVT OBDII Automated Test Outcomes	15
5.2 AVT OBDII Manual Test	15
5.2.1 AVT OBDII Manual Test Outcomes	16
Appendix A - Technical Support.....	17
Appendix B – Warranty Information	17
Appendix C - List of Acronyms.....	18

2 Safety First

It is essential that the user read this document carefully before using the hardware.

Adapter Validation Tool (AVT) is to be used by those trained in the troubleshooting and diagnostics of light-duty through heavy-duty vehicles and equipment. The user is assumed to have a very good understanding of the electronic systems contained on these and the potential hazards related to working in a shop-floor environment.

DG Technologies understands that there are numerous safety hazards that cannot be foreseen, so we recommend that the user read and follow all safety messages in this manual, on all of your shop equipment, from your vehicle manuals, as well as internal shop documents and operating procedures.



- ❑ Always block all wheels when testing.
- ❑ Use extreme caution when working around electricity. When diagnosing any vehicle, there is the risk of electric shock both from battery-level voltage, vehicle voltages, and from building voltage.
- ❑ Do not smoke or allow sparks or open flames near any part of the vehicle fueling system or vehicle batteries.
- ❑ Always work in an adequately ventilated area, and route vehicle exhaust outdoors.
- ❑ Do not use this product in an environment where fuel, fuel vapor, exhaust fumes, or other potentially hazardous liquids, solids, or gas/vapors could collect and/or possibly ignite, such as in an unventilated area or other confined space, including below-ground areas.


3 Troubleshooting Diagnostic Tool with Adapter Validation Tool (AVT)

If your OEM application is having trouble communicating with the Diagnostic Tool, you can use the Adapter Validation Tool (AVT) to help troubleshoot this problem. AVT allows you to determine:

- If your drivers are installed correctly.
- If a connection to your tool can be made.
- Detection of data link activity.
- ❑ **AVT cannot be used to troubleshoot whether there are problems with setting up the OEM application and the Diagnostic Tool.**

3.1 Adapter Validation Tool Startup

A shortcut to *Adapter Validation Tool* can be found the desktop or in the Start Menu.



AVT Launcher

3.2 Select the Correct AVT Launcher Button

The functionality of AVT has been split out into two different applications. One is targeted for medium or heavy-duty vehicles and connects to the vehicle using TMC RP1210 compatible tools. The other is targeted for light or medium duty vehicles and connects to the vehicle using SAE J2534 tools.

3.2.1 MD/HD Button



MD/HD Button

Click on the MD/HD truck button if you are doing diagnostics on a medium or heavy-duty vehicle. The most common protocols for these vehicles are J1939, ISO15765 and J1587/J1708.

3.2.2 OBDII Button



OBDII Button

Click on the OBDII car selection if you have an OBDII vehicle. This is most typically found on light and medium-duty vehicles. CAN/ISO15765, J1850, ISO9141, and ISO14230 are the most common protocols.

4 Adapter Validation Tool for Heavy and Medium-Duty Vehicles

This section covers all TMC RP1210 tools. The automated test mode is displayed by default when the software is launched. This allows for quick scanning of the most common protocols associated found on HD vehicles.

Should you need to test individual protocols using specific baud rates you can do this by accessing the **Advanced Test** functionality.

4.1 AVT HD Automated Testing

DG Technologies - Adapter Validation Tool (MD/HD)

Vendor
DGDPAXL - DG Technologies DPA XL

Device
1 - DPA XL USB - USB

Language / Idioma / Langage
☒ English ☐ Espanol ☐ Francais

Fix RP121032.INI File

Test Connections

Advanced Test

RP1210 Status Window (PC - VDA)
DG Technologies - Adapter Validation Tool (MD/HD)

Protocol Status


CAN 1 J1708 Help

CAN 2

CAN 3

CAN 4

Red Connection not opened
Green Connection opened AND data detected
Orange Connection opened no data read
Black Not supported

 **DG TECHNOLOGIES**
Vehicle Network Solutions

248.888.2000
www.dgtech.com
sales@dgtech.com

AVT HD Automated Mode


4.1.1 Select the Diagnostic Tool

To establish a connection to a tool you must select the **Vendor** and the **Device ID** associated with your tool using the two drop down boxes at the top of the screen.

4.1.2 Run the Automated Test


Click the **Test Connections** selection after your hardware has been identified. Depending on the results of the test, both the **RP1210 Status Window Message** will turn **green** (pass) or **red** (fail).

4.1.3 RP1210 Status Window (PC – VDA)



AVT HD Automated Test RP1210 Status Window (PC-VDA)

If the **RP1210 Status Window** turns **red**, there is a problem causing the PC to not communicate with the Diagnostic Tool. Disconnect the Diagnostic Tool from the vehicle and PC; then reconnect them. If you are using a wired connection to the computer, try using another port or cable to help identify if you are dealing with a hardware problem. Should your connection to the diagnostic tool fail a new window with troubleshooting instructions will be displayed to help in taking steps to correcting the problem.



Status = Failed Connection to VDA

If the **RP1210 Status Window** turns **green**, then the PC is connecting to the Diagnostic Tool.

DG Technologies - Adapter Validation Tool (MD/HD)

Vendor
DGDPAXL - DG Technologies DPA XL

Device
1 - DPA XL USB - USB

Language / Idioma / Langage
☒ English ☐ Espanol ☐ Francais

Fix RP121032.INI File

Test Connections

Advanced Test

API: 5.0, DLL: 3.03, Firmware: 3.04


RP1210 Status Window (PC - VDA)

CAN:Channel=4,Baud=Auto Connection Returned: 603
CAN 1 - RP1210 ReadMessage - SUCCESS. There were 2505 messages seen in 5 seconds.
[RP1210_ClientDisconnect] ERR_HARDWARE_NOT_RESPONDING indicates that the device hardware J1708 Connection Returned: 142

Protocol Status

CAN 1	250000	J1708		Help
CAN 2				
CAN 3				
CAN 4				

Red Connection not opened
Green Connection opened AND data detected
Orange Connection opened no data read
Black Not supported

 **DG TECHNOLOGIES**
Vehicle Network Solutions

248.888.2000
www.dgtech.com
sales@dgtech.com

4.1.4 Protocol Status

Protocol Status

CAN 1

CAN 2

CAN 3

CAN 4

J1708

Help

Red Connection not opened
Green Connection opened AND data detected
Orange Connection opened no data read
Black Not supported

AVT HD Automated Test Protocol Status Section

The **Protocol Status** section of the automated test screen shows details about what protocols are supported by the tool, what baud rate they are running at and if data was detected on them. Up to 4 CAN channels can be scanned, as well as J1708. The colors of the protocol status bars are color coded for ease of understanding.

Red		Unable to connect to protocol. This color should be displayed when the connection to the tool failed.
Green		Successfully connected to protocol. The baud rate was determined, and data was received. The baud rate that the link is running at will be displayed in the status bar of the protocol
Orange		Successfully connected to protocol. The baud rate may have been able to be determined, but NO data was received.
Black		Protocol not supported by the tool selected.

AVT HD Protocol Status Color Coding

Protocol Status

CAN 1 Unknown

CAN 2 Unknown

CAN 3

CAN 4

J1708 9600

Help

Red Connection not opened
Green Connection opened AND data detected
Orange Connection opened no data read
Black Not supported

Example of Automated AVT HD Orange and Black Protocol Statuses

Protocol Status

CAN 1 250000

CAN 2 500000

CAN 3 250000

CAN 4 250000

J1708 9600

Help


Red Connection not opened
Green Connection opened AND data detected
Orange Connection opened no data read
Black Not supported

Example of Automated AVT HD Green Protocol Statuses

4.2 Advanced Testing Dialog (Vendor/Device/Protocol)

Should you need to scan other protocols to see if they are present, you can do so by using the Advanced Test Interface. This allows you to choose baud rate and channel that a Vendor/Tool supports. This option is mainly used for engineering purposes and requires some knowledge of the vehicle's diagnostic link setup.

Choosing the **Advanced Test** button on the main AVT HD will bring up the Advance Test interface. The Vendor and Device functionality of the Automated Test are also used in the Advanced Test. In the sections below the other selections are briefly described. You will need an understanding of the TMC RP1210 API to fully understand all these settings. Again, this is an engineering level tool and should be used accordingly.

 DG Technologies - AVT (MD/HD) - Advanced Test

Vendor

DGDPAXL - DG Technologies DPA XL

Device

1 - DPA XL USB - USB

Protocol

CAN

☒ Vendor Supports CAN Auto Baud

Baud Rate

Auto

☒ Use Baud Rate

Channel

1

☐ Use Channel

Protocols Supporting Baud=XXX

☒ CAN

☒ J1708

☒ J1939

☒ ISO15765

Run Advanced Test

Back

Help

Quit

RP1210 Status Window (PC - VDA)

RP1210 Data Message Window (VDA - Vehicle)

AVT HD Advanced Test Dialog

4.2.1 Baud Rate Drop Down List Box

The **Baud Rate** drop down list box allows the user to select one of the supported protocol speeds for the selected protocol. The entries in this list box come from the VDA vendor's INI file. Click the **Use Baud Rate** checkbox to activate a "Protocol:Baud=XXX" connection. If both the **Use Baud Rate** and **Use Channel** checkboxes are checked, then AVT will initiate a "Protocol:Baud=XXX;Channel=X" connection.

4.2.2 Channel Drop Down List Box

The **Channel** drop down list box allows the user to select one of the supported channels for the selected device. The entries in this list box come from the VDA vendor's INI file. Click the **Use Channel** checkbox to activate a "Protocol:Channel=X" connection. If both the **Use Baud Rate** and **Use Channel** checkboxes are checked, then AVT will initiate a "Protocol:Baud=XXX;Channel=X" connection.

4.2.3 Vendor Supports CAN Auto Baud Checkbox

This checkbox indicates whether the API supports CAN (CAN, J1939, ISO15765) automatic baud detection. Even though this variable may be set to TRUE, the next four fields indicate whether the API supports Baud=XXX connect formats for CAN, J1939, and ISO15765. This field is just an informational field, and not all VDA vendors will support this feature.

4.2.4 Protocols Supporting Baud=XXX

These checkboxes indicate whether the API supports setting a specific baud rate (or automatic baud detection) for a specific protocol. These entries come from the VDA vendor's INI file. These fields are just for informational purposes. Not all VDA vendors will support this feature.

4.2.5 Advanced Testing Commands – No Error Checking

When using this dialog box to initiate an advanced test, there is no error checking done to prevent the user from initiating a "Baud=XXX" or "Channel=X" connection to a VDA even if the vendor does not support that connection format.

4.2.6 RP1210 Data Message Window

When data is read from the data link the message data is displayed here and the window is turned **green**. If no data is read the window is turned **red**.

RP1210 Data Message Window (VDA - Vehicle)

```
TS[1644571]:[01][18][FE][CA][00][FF][FF][64][00][02][00][FF][FF]
TS[1644571]:[01][0C][F0][02][03][D0][00][00][FF][F7][00][00][03]
TS[1644579]:[01][18][FE][EE][00][9D][FF][FF][FF][FF][FF][FF][FF]
TS[1644580]:[01][0C][F0][02][03][D0][00][00][FF][F7][00][00][03]
TS[1644590]:[01][0C][F0][02][03][D0][00][00][FF][F7][00][00][03]
TS[1644595]:[01][0C][F0][0C][03][00]
```

AVT HD Advanced Test – RP1210 Data Message Window (VDA – Vehicle) indication of success with data.


4.3 Not Seeing Diagnostic Tool device in HD OEM Application VDA Selection List

If you have installed the Diagnostic Tool drivers and can get AVT to a RP1210 Status of Green you should be able to configure your diagnostic application to use the Diagnostic Tool. If your diagnostic application does not display in the VDA selection dialog box, this could indicate one of three things:

1. The application is not RP1210 compliant and does not work with the Diagnostic Tool.
 - a. Some applications require a specific, proprietary adapter.
2. Application is compliant, but Diagnostic Tool does not support the protocol needed.
3. Problem with the main INI file – See Fix INI file.
 - a. Some VDAs create issues with the INI file when they install/uninstall.
 - b. Many OEM diagnostic applications are aware of this issue and can read through the errors.

4.3.1 Fix INI Application

When the AVT HD software is launched, you will be told if a problem exists in the RP121032.INI file.



AVT HD dialog displayed at program launch notifying of RP121032.ini problems.

If you wish to fix this issue, which is **strongly recommended**, press the **Fix RP121032.INI File** button on the main ATV HD screen. If your PC is running Windows 10 or Windows 7, you will be prompted for administrator privileges. The following is the dialog box that will appear when AVT is launched and a problem is found in the main INI file.




AVT HD Fix RP121032.INI File Button

When you choose the **Fix RP121032.INI File** selection, AVT will bring up a separate program called **Fix INI** that will allow you to view and fix the INI file if there are errors detected.


The **Current RP121032.INI File (Untouched)** box shows what is currently in the global file that vendors are defined in. In the example below this is colored yellow to indicate that there is a problem with it.

The **Proposed RP121032.INI File (With Proposed Changes)** box shows what the Fix INI program will do to correct formatting errors in this file. Only after you select the **Make Changes** button will the application save the changes to the file.



Fix INI showing original and edited RP121032.ini file.


If you choose the **Make Changes** button you will be presented with a message box indicating that the edits were successfully made or not. Should you want to return to the unedited version of the RP121032.ini file the original file is saved on the computer with a unique file name.



Dialog confirming that changes were successfully made to the RP121032.ini file.

5 AVT (OBDII) – Adapter Validation Tool for Light and Medium-Duty Vehicles

This selection covers all J2534 tools. By default, AVT OBDII launches in Automated Test mode. All J2534 protocols and at a variety of common baud rates are scanned in this mode to determine what protocols are present on the vehicle. To switch between Automated Test mode and Manual Test mode use the menu bar.



AVT OBDII Automated Test

5.1 AVT OBDII Automated Test




5.1.1 Configure Device

To configure the Device currently selected choose this button. This will launch the vendor supplied configuration application. This applications contents and appearance vary by vendor so consult the tools documentation on how to use this software.

5.1.2 Run Test

When you choose this button all the common OBDII protocols and baud rates are scanned if a connection to the tool can be established. Colored coded lines between the PC, tool and vehicle images on the screen keep you informed of what is going on and the status of each step.

- Ensure proper connections of Diagnostic Tool to vehicle and PC.
- Turn ignition key to “On” and click on **Run Test**.
- The connection to the tool will be attempted and if established the OBDII protocols will be scanned.
- This is a Pass/Fail test. During the test process the line colors will change. Look at the table and images below to gain an understanding of what the different colors mean during AVT OBDII Automated Test mode.
- Click on **Exit** when done.

Red		Unable to connect to tool or no protocols detected
Green		Green Line from indicates a successful test of either the tool or protocol sections
Orange		Connection to tool or protocol being attempted

AVT OBDII Automated Mode Color Coding Chart


5.1.2.1 Run Test Screen Examples




AVT OBDII Automated Test attempting to connect to tool



AVT OBDII Automated Test example of failed connection to tool



AVT OBDII Automated Test example of successful connection to tool and vehicle protocol CAN_CH1 being scanned.



AVT OBDII Automated Test example of successful connection to tool and vehicle protocol.

5.1.3 AVT OBDII Automated Test Outcomes

Should the connection to the tool fail no protocol connections will be attempted. A screen detailing what steps you can take to try to fix the tool to PC connection failure will be displayed.

- Ensure both connections at each end of USB cable, between the J2534 device and the PC, are secure.
- Ensure J2534 device was properly installed on PC and possibly re-install.
- Ensure the J2534 device is powered with power light illuminated.
- If problem persists, try a different cable.
- If after following the **Test Results Discussion and Next Steps** screen, you cannot get the adapter to read data contact the tool manufacture's technical support.

5.2 AVT OBDII Manual Test

This is the engineering interface to the J2534 tool selected. An understanding of the vehicle network and the SAE J2534 API will be needed to successfully use this part of the application. Using the **OBD II** protocol selection means that AVT will attempt to connect using all OBDII protocols that the selected adapter supports (i.e. J1850VPW, ISO9141, ISO14230, ISO15765, etc.) and with all OBDII options and OBDII speeds for that protocol (i.e. CAN 1Mb 11-bit, CAN 1Mb 29-bit, CAN 500Kb 11-bit, CAN 500Kb 29-bit, etc.). DG recommends using the OBDII protocol setting initially since all vehicles after 1996 must support an OBDII protocol.

Device:

Protocol:

J2534 Status Window (Tests PC to VDA Connection)

```
Read any broadcast messages...
Connecting with CAN_CH1 [29 bit]...
Read any broadcast messages...
SUCCESS. There were 187 messages seen in 2000 milliseconds at protocol baud rate of
```

J2534 Data Message Window (Tests VDA to Vehicle Connection)

```
[0C] [F0] [03] [00] [D8] [FE] [00] [FF] [FF] [1F] [7C] [7D]
TS[243299500]PrID=[0x9000]RxS=[0x100]TxF=[0x00]DS=[12]EDI=[12]
[08] [FE] [6E] [0B] [FF] [FE] [FF] [FE] [FF] [FE] [FF] [FE]
TS[243300125]PrID=[0x9000]RxS=[0x100]TxF=[0x00]DS=[12]EDI=[12]
[18] [FE] [F2] [00] [00] [00] [00] [00] [9D] [02] [FE] [FF]
```



DG TECHNOLOGIES
Vehicle Network Solutions

248.888.2000
www.dgtech.com
sales@dgtech.com

5.2.1 AVT OBDII Manual Test Outcomes

If the connection to the tool can be established, then the connection to the Protocol specified in the drop-down box will be attempted. The user is responsible for knowing details about what protocols are present on the vehicle if choosing anything other than OBDII. Detailed information about the connection status to the tool will be displayed in the **J2534 Status Window (Test PC to VDA Connection)** window. Details about the data link messages read will be displayed in the **J2534 Data Message Window (Tests VDA to Vehicle Connection)** window.

If a connection cannot be established, then the window will turn **red**. A window with the color of **green** indicates success.

Appendix A - Technical Support

After reading and following the troubleshooting and validation procedures in this document please check the FAQ page at www.dgtech.com/faqs. If you are still not able to resolve an issue, please feel free to contact DG technical support. For users in the United States, technical support is available from 9 a.m. to 5 p.m. Eastern Time. You may also fax or e-mail your questions to us. For prompt assistance, please include your voice telephone number and the serial number located on your DG Technologies product.



DG Technologies Technical Support

Phone: (248) 888-2000
Fax: (248) 888-9977
E-mail: techsupp@dgtech.com
Web site: www.dgtech.com/tech-support

Users not residing in the United States should contact your local DG representative or email techsupp@dgtech.com.

Appendix B – Warranty Information

This program is provided AS IS and is free-of-charge for DG's product owners. It was intended to be a value-added feature to enhance the value of DG's product line.

DG Technologies disclaims all warranties, either expresses or implied, including any implied warranty of merchantability or fitness for any particular purpose. DG Technologies shall have no liability to anyone for incidental or consequential damages for merchandise which is provided AS IS.

DG Technologies makes no warranty as to the performance of this product. DG Technologies has placed this program through extensive testing, however as with any software, there could be deficiencies. Therefore, we cannot guarantee that any parameters displayed are accurate.

We hope that you enjoy this tool and find it of value. If you find deficiencies, or have requests for the addition of non-OEM-proprietary functionality, please do not hesitate to contact us at:

DG Technologies
33604 West 8 Mile Road
Farmington Hills, MI 48335
Phone (248) 888-2000
www.dgtech.com
techsupp@dgtech.com

Appendix C - List of Acronyms

Various acronyms have been used throughout this document.

Acronym	Description
API	Application Programming Interface
AVT	Adapter Validation Tool
CAN	Controller Area Network
CD	Compact Disk
CD-ROM	Compact Disk - Read Only Memory
DG	DG Technologies
DPA	DG Technologies Protocol Adapter
DTC	Diagnostic Trouble Codes
ID	Identification
ISO	International Standards Organization
LED	Light Emitting Diode
OBD	On Board Diagnostics
OEM	Original Equipment Manufacturer
PC	Personal Computer
RAM	Random Access Memory
RP	Recommended Practice (see TMC)
SAE	Society of Automotive Engineers
TMC	Technology and Maintenance Council
UAC	User Account Control
USB	Universal Serial Bus
VDA	Vehicle Datalink Adapter